Please follow this guide to connect to Hosted ASTS Bridge service to access the test environment of the MOEX Equity & Bond, FX and Money Markets via Internet:

Check the connection addresses

Execute consecutively the following commands in the command line window:

To check availability of test servers of the Equity & Bond Market:

```
telnet 91.208.232.161 15014
```

telnet 91.208.232.162 15014

telnet 91.208.232.161 15024

telnet 91.208.232.162 15024

To check availability of test servers of the FX Market:

```
telnet 91.208.232.161 15010
```

telnet 91.208.232.162 15010

telnet 91.208.232.161 15020

telnet 91.208.232.162 15020

To check availability of test servers of the Money Market:

```
telnet 91.208.232.161 15012
```

telnet 91.208.232.162 15012

- + After every command is executed, black screen with a blinking cursor should appear that means successful connection has been made. To execute the next command, press "ctrl"+"C".
- if the error message appears that says *«telnet is recognized as an internal or external command"*, please contact your system administrator to check accessibility of addresses and connection ports.
- if the error message appears that says "Could not open connection to the host, on port: Connect failed" please contact your system administrator to receive authorisation to access the pairs of addresses and connectivity ports.

Make sure connection setup is correct

We recommend changing the connection setup when the markets are closed and check in advance network accessibility of connection addresses.

To connect to test gateways of the Equity & Bond Market:

INET environment:

- parameter "HOST" is set to: 91.208.232.161:15014, 91.208.232.162:15014
- parameter "SERVER" is set to: EQ_TEST
- to connect to clearing, parameter "SERVER" is set to EQ_TEST_RISK

UAT environment:

- parameter "HOST is set to: 91.208.232.161:15024, 91.208.232.162:15024
- parameter "SERVER" is set to: EQ_UAT
- to connect to clearing, parameter "SERVER" is set to EQ_UAT_RISK

To connect to test gateways of the FX Market:

INETCUR environment:

- parameter "HOST" is set to: 91.208.232.161:15010, 91.208.232.162:15010
- parameter "SERVER" is set to: CUR_TEST
- to connect to clearing, parameter "SERVER" is set to CUR_TEST_RISK

UATCUR environment:

- parameter "HOST" is set to: 91.208.232.161:15020, 91.208.232.162:15020
- parameter "SERVER" is set to: CUR_UAT
- to connect to clearing, parameter "SERVER" is set to CUR_UAT_RISK

To connect to test gateways of the Money Market:

INETGKO environment:

- parameter "HOST" is set to: 91.208.232.161:15012, 91.208.232.162:15012
- parameter "SERVER" is set to: GKO_TEST

! If parameter "HOST" has already set to a value that differs from servers with addresses 91.208.232.161 μ 91.208.232.162, new setup should be agreed with your system administrator.